



7-Mode Transition Tool 3.2

Installation and Setup Guide

February 2017 | 215-11977-A0
doccomments@netapp.com

Contents

Transition to ONTAP by using the 7-Mode Transition Tool	4
Comparison of copy-free transition and copy-based transition	4
Interfaces and transition capabilities available on Windows and Linux	5
Installing or uninstalling the 7-Mode Transition Tool on a Windows	
system	7
System requirements for installing the 7-Mode Transition Tool on Windows	
systems	7
Installing the 7-Mode Transition Tool on a Windows system	9
Enabling login for users not part of the Administrator group	9
Logging in to the 7-Mode Transition Tool	10
Uninstalling the 7-Mode Transition Tool on a Windows system	11
Installing or uninstalling the 7-Mode Transition Tool on Linux	
(Copy-based transition only)	12
System requirements for installing 7-Mode Transition Tool on Linux	12
Installing 7-Mode Transition Tool on Linux	12
Uninstalling 7-Mode Transition Tool on Linux	13
Modifying the configuration options of the 7-Mode Transition Tool	15
Troubleshooting issues	16
Tool installation fails with an incompatible OS error	16
Installation or uninstallation of the 7-Mode Transition Tool is blocked	16
Reinstalling or upgrading the 7-Mode Transition Tool fails on Windows system	17
Windows Program Compatibility Assistant notification displayed while	
installing the tool	17
Copyright information	18
Trademark information	19
How to send comments about documentation and receive update	
 notifications	20
Index	21

Transition to ONTAP by using the 7-Mode Transition Tool

The 7-Mode Transition Tool enables you to collect inventory of 7-Mode controllers, hosts, switches, and applications, and assess their readiness for transition. After assessment, you can migrate your data and configurations from 7-Mode to ONTAP either by using copy-free transition or copy-based transition.

Comparison of copy-free transition and copy-based transition

You can use the 7-Mode Transition Tool to migrate your data and configurations from 7-Mode to ONTAP by using either copy-based transition or copy-free transition. It is important to understand the differences between the two methods before transition.

Parameter	Copy-free transition	Copy-based transition
Unit of transition	HA pair	Group of volumes
Hardware requirement	Disk shelves are reused	New disks shelves and disks to host the transitioned volumes
Platform requirement	Supported only on mid-level and high-level platforms NetApp Interoperability Matrix Tool	Supported on all platforms
Transition duration	Overall, shorter transition duration (no data copy required)	Longer duration (initial baseline and update transfer time varies based on workload, network bandwidth, and data capacity being migrated)

Parameter	Copy-free transition	Copy-based transition
Disruption to data access	<p>In the range of hours</p> <p>Important: In most cases, the storage cutover time can be 3 through 8 hours. Cutover time includes the time taken by the tool to perform two automated operations—the export and halt operation and the import operation—as well as the time taken for manually cabling the disk shelves to the new controllers. The export and halt operation and the import operation together can take up to 2 hours. Cabling of the disk shelves can take from 1 hour through 6 hours.</p> <p>This cutover time guidance does not include the time taken for the required preproduction testing and assumes an error-free transition without unexpected failures such as a disk failure.</p>	In the range of minutes

Interfaces and transition capabilities available on Windows and Linux

You can install the 7-Mode Transition Tool on Windows or Linux. You must be aware of the features and the user interfaces that are supported before installing the 7-Mode Transition Tool.

Migration method	Feature	Supported on Windows	Supported on Linux
Copy-free transition	Graphical user interface (GUI)	Yes	No
	Command-line interface (CLI)	No You cannot use the CLI for creating and managing projects; however, you have to run certain commands, such as commands for ignoring blocking errors, during the transition from the Windows CLI.	No
	Collect and assess	Yes	No

6 | Installation and Setup Guide

Migration method	Feature	Supported on Windows	Supported on Linux
Copy-based transition	GUI	Yes	No
	CLI	Yes	Yes
	Collect and assess	Yes	No

Installing or uninstalling the 7-Mode Transition Tool on a Windows system

You can download and install the 7-Mode Transition Tool on a Windows system by using the standard wizard-based installer. However, if you have a previously installed version of the 7-Mode Transition Tool, you need to be aware of certain prerequisites before doing so.

- If you have a 7-Mode Transition Tool version earlier than 3.0 installed in your system, then you need to uninstall that 7-Mode Transition Tool before installing 7-Mode Transition Tool 3.2. You must create a backup of the log files if you choose to retain the log files during uninstallation. The 7-Mode Transition Tool installer installs the tool to the same folder and overwrites the log files the next time you run it.
- If you have 7-Mode Transition Tool 3.0 or later installed in your system, then the following conditions must be met before installing 7-Mode Transition Tool 3.2:
 - All existing copy-based transition projects must either be completed or aborted.
 - All existing copy-free transition projects must either be completed or rollback complete.

System requirements for installing the 7-Mode Transition Tool on Windows systems

You must ensure that the Windows host meets the required configuration to install and run the 7-Mode Transition Tool.

Hardware requirements

- Dual-core x64 processor, 1.0 GHz or more
- 8 GB RAM
- 40 GB free disk space

Software requirements

- Your 64-bit Windows system must be running one of the following operating system versions:
 - Windows 7 Enterprise
 - Windows 7 Enterprise SP1
 - Windows Server 2008 Standard
 - Windows Server 2008 R2 Standard
 - Windows Server 2008 R2 Enterprise with SP1
 - Windows Server 2012 Standard
 - Windows Server 2012 R2 Standard
 - Windows 8.1 Enterprise

Note: You can use a Windows virtual machine that meets the required software and hardware requirements to install the 7-Mode Transition Tool.

- 64-bit Oracle Java Runtime Environment (JRE) 1.8 update 112

Note: If the Windows host does not have JRE or has 32-bit JRE installed, the 7-Mode Transition Tool installer automatically installs 64-bit JRE 1.8 update 112. If an earlier version of 64-bit JRE is installed, the installer automatically updates it to JRE 1.8 update 112.

When JRE is updated automatically, the other applications that require earlier versions of JRE might be affected.

Note: With JRE versions 1.8 update 46 or later (which includes JRE 1.8 update 112), for 7-Mode Transition Tool to communicate with 7-Mode and ONTAP, the SSL key length on the 7-Mode and ONTAP systems must be at least 1024. For more information, see the Knowledgebase article: [KB ID 000022724](#).

Server configuration requirements

To access the web interface, the Windows system on which the tool is installed must be configured as follows:

- Port 8444 of the 7-Mode Transition Tool server must be available.

If port 8444 is not available, or if you want to use a different port, you must change the port specified by the `tool.https.port` parameter in the `$INSTALL_DIR\etc\conf\transition-tool.conf` file.

The best practice is to use HTTPS for accessing the web interface. However, if you want to use HTTP for accessing the web interface, port 8088 must be available. For an alternative to port 8088, you must change the port specified by the `tool.http.port` parameter in the `transition-tool.conf` file.

Note: You must restart the 7-Mode Transition Tool service after changing the port in the configuration file.

- The firewall should be either turned off or configured to allow traffic on the port that is used to access the tool.

To transition netgroups and CIFS local users and groups, the following requirements must be met:

- Port 8088 of the 7-Mode Transition Tool must be available.

For an alternative to port 8088, you must change the port specified by the `tool.http.port` parameter in the `transition-tool.conf` file, and then restart the 7-Mode Transition Tool service.

- Each node in the cluster must have at least one data LIF configured for the target SVM.
- All SVM data LIFs must be able to communicate with the 7-Mode Transition Tool port 8088 or the port specified by the `tool.http.port` parameter in the `transition-tool.conf` file.

Note: You must ensure that firewalls do not block this traffic.

Client (web interface) requirements

The system that accesses the web interface must have the following:

- One of the following web browsers:
 - Microsoft Internet Explorer 9, 10, or 11
 - Google Chrome 27 or later
 - Mozilla Firefox 20 or later

All browsers must be TLS enabled.

Note: If you are using Microsoft Internet Explorer as your web browser, you must disable SSLv2.

- A screen resolution of 1280 × 1024 or higher

Every time you install a new version of the tool, you must clear the browser cache by pressing Ctrl+F5 on the system.

Related information

[NetApp Interoperability](#)

Installing the 7-Mode Transition Tool on a Windows system

You can install the 7-Mode Transition Tool on a Windows system by using the wizard-based installer.

Before you begin

- You must have reviewed the system requirements for the 7-Mode Transition Tool.
[System requirements for the 7-Mode Transition Tool on Windows](#)
- You must have the necessary administrator privileges to install and launch the application.
- You must have cleared the browser cache by pressing Ctrl+F5.
You must clear the cache every time you install a new version of the tool.

Steps

1. Download the software from the NetApp Support Site.
[NetApp Downloads: Software](#)
2. Run the `NetApp_7ModeTransitionTool_Setup.exe` file.
3. In the **7-Mode Transition Tool Setup** welcome screen, click **Next**.
4. Follow the on-screen prompts to continue with the installation.
5. Optional: Select **Launch the tool** to open the 7-Mode Transition Tool immediately after the installation.
6. Click **Finish** to complete the installation.

Enabling login for users not part of the Administrator group

By default, users must be members of the Administrator group on the Windows system on which the 7-Mode Transition Tool is installed. At any time, you can enable login for users who are not members of the Administrators group and who cannot install the tool but are authenticated to use the Windows system on which the tool is installed.

Steps

1. Log in to the Windows host using admin privileges.
2. Modify the configuration file of the tool to enable users who are not part of the Administrator group to log in to the tool:
 - a. Open the `\etc\conf\transition-tool.conf` file from the installation directory.

- b. Set the value of the `tool.login.non.admin.enabled` parameter in the `transition-tool.conf` file to `true`.
 - c. Save the file.
3. Restart the transition service.
 - a. Click **Start > Control Panel > System and Services > Administrative Tools > Services**.
 - b. Right-click the **NetApp 7-Mode Transition Tool** service and click **Stop**.
 - c. Right-click the **NetApp 7-Mode Transition Tool** service again and click **Start**.

Related tasks

[Modifying the configuration options of the 7-Mode Transition Tool](#) on page 15

Logging in to the 7-Mode Transition Tool

You can log in to the 7-Mode Transition Tool (web interface) by using your credentials of the Windows system on which the tool is installed. The procedure to log in varies depending on the type of user credentials you have.

About this task

Guest users are not allowed to log in to the tool.

Steps

1. Navigate to the login page:

If you are a...	Then...
User who is a member of the Administrator group and if you are accessing the tool (web interface) from the server on which it was installed	Double-click the 7-Mode Transition Tool icon on your desktop.
User who is a member of the Administrator group and if you have not installed the tool	Use a supported browser to navigate to one of the following URLs: <ul style="list-style-type: none"> • <code>https://IP_address:port/transition</code> • <code>http://IP_address:port/transition</code> <p><i>IP_address</i> is the IP address of the server and <i>port</i> can be 8443 (default), the value specified for <code>tool.https.port</code>, or 8088, the value specified for the <code>tool.http.port</code> parameter in the <code>transition-tool.conf</code> file.</p>
User who is a member of the Administrator group and if you are accessing the tool (web interface) from another computer	Use a supported browser to navigate to one of the following URLs: <ul style="list-style-type: none"> • <code>https://IP_address:port/transition</code> • <code>http://IP_address:port/transition</code> <p><i>IP_address</i> is the IP address of the server and <i>port</i> can be 8443 (default), the value specified for <code>tool.https.port</code>, or 8088, the value specified for the <code>tool.http.port</code> parameter in the <code>transition-tool.conf</code> file.</p>

If you are a...	Then...
User who is not a member of the Administrator group and if you are accessing the tool (web interface) either from the server on which it was installed or from another computer	<p>Use a supported browser to navigate to one of the following URLs:</p> <ul style="list-style-type: none"> • <code>https://IP_address:port/transition</code> • <code>http://IP_address:port/transition</code> <p><i>IP_address</i> is the IP address of the server and <i>port</i> can be 8443 (default), the value specified for the <code>tool.https.port</code>, or 8088, the value specified for the <code>tool.http.port</code> parameter in the <code>transition-tool.conf</code> file.</p>

2. If the browser displays a message about the self-signed SSL certificate, then accept the self-signed certificate to continue.
3. Log in to the web interface by using the credentials of the Windows system in which the tool is installed.

Uninstalling the 7-Mode Transition Tool on a Windows system

You can uninstall the 7-Mode Transition Tool by using the Windows Uninstall program utility.

Before you begin

- You must have completed all in-progress transitions.
 - Important:** Installing a newer version or reinstalling the same version of the tool does not allow you to access the transition operations started by the uninstalled instance.
- If the 7-Mode Transition Tool is running, it must be closed.

About this task

Java Runtime Environment (JRE) is not removed as part of the uninstallation.

Steps

1. Click **Start > Control Panel > Uninstall a program**.
2. Select the 7-Mode Transition Tool from the list of programs and click **Uninstall**.
3. Complete the steps in the wizard to uninstall the 7-Mode Transition Tool.

You can choose to save the project details and logs for troubleshooting purposes.

After you finish

You must create a backup of the log files if you choose to retain the log files during uninstallation. The 7-Mode Transition Tool installer installs the tool to the same folder and overwrites the log files the next time you run it.

Installing or uninstalling the 7-Mode Transition Tool on Linux (Copy-based transition only)

You can download and install the 7-Mode Transition Tool on a Linux system by using the command-line interface. When required, you can uninstall the 7-Mode Transition Tool.

You can perform only copy-based transition on a Linux system. Copy-free transition is not supported on Linux.

Important: The 7-Mode Transition Tool web interface is not supported on Linux. You must use the CLI to perform copy-based transition tasks on a Linux system.

System requirements for installing 7-Mode Transition Tool on Linux

You must ensure that the Linux host has the required configuration to install and run the 7-Mode Transition Tool.

Hardware requirements

- Dual-core x64 processor, 1.0 GHz or more
- 8 GB RAM
- 40 GB free disk space

Software requirements

- Your Linux system must be running one of the following:
 - Red Hat Enterprise Linux 5.6
 - Red Hat Enterprise Linux 6.0
 - CentOS release 6.4

Note: You can use a Linux virtual machine that meets the required software and hardware requirements to install the 7-Mode Transition Tool.

- 64-bit Oracle JRE 1.8 update 45
- 7-zip utility (`rpmforge-release-0.3.6-1.el5.rf.x86_64.rpm`)

Note: JRE 1.8 and the 7-zip utility must be installed on the Linux system before configuring the 7-Mode Transition Tool.

Installing 7-Mode Transition Tool on Linux

You can install the 7-Mode Transition Tool on your Linux system by using the command-line interface.

Before you begin

- You must have reviewed the system requirements for 7-Mode transition tool.
[System requirements for installing 7-Mode Transition Tool on Linux](#)

- You must have root user privileges to install and launch the application.

Steps

1. Download the `tar.gz` file from the NetApp Support Site.

[NetApp Downloads: Software](#)

2. Extract the `tar.gz` file to a directory in the Linux system:

```
tar -xzvf NetApp_7ModeTransitionTool_Setup.tar.gz -C directory_path
```

3. Change the directory to the installation directory:

```
cd directory_path/NetApp_7ModeTransitionTool
```

4. Configure the 7-Mode Transition Tool server:

```
./configure
```

This starts the 7-Mode Transition Tool service on the Linux system.

5. Verify that the 7-Mode Transition Tool service is running on the Linux system:

```
service transition-service status
```

Example

```
bash-4.2# tar -xzvf NetApp_7ModeTransitionTool_Setup.tar.gz -C /
root/Downloads/extracted_folder
bash-4.2# cd /root/Downloads/extracted_folder/
NetApp_7ModeTransitionTool
bash-4.2# ./configure
bash-4.2# service transition-service status
The transition-service (NetApp 7-Mode Transition Tool server) is
running. PID=38384.
```

Related information

[NetApp Support](#)

Uninstalling 7-Mode Transition Tool on Linux

You can uninstall the 7-Mode Transition Tool on Linux by using the command-line interface.

Before you begin

- You must have completed all in-progress transitions.
 - Important:** Installing a newer version or reinstalling the same version of the tool does not allow you to access the transition operations started by the uninstalled instance.
- If the 7-Mode Transition Tool is running, it must be stopped.

About this task

JRE is not removed as part of the uninstallation.

Steps

1. Uninstall 7-Mode Transition Tool by running the following command from the location where you extracted the 7-Mode Transition Tool:

```
./unconfigure
```

2. Remove the 7-Mode Transition Tool directory:

a. `cd ..`

b. `rm -rf NetApp_7ModeTransitionTool`

Example

```
bash-4.2# cd /root/Downloads/extracted_folder/  
NetApp_7ModeTransitionTool  
bash-4.2# ./unconfigure  
bash-4.2# cd ..  
bash-4.2# rm -rf NetApp_7ModeTransitionTool
```

Modifying the configuration options of the 7-Mode Transition Tool

You can edit the `$INSTALL_DIR\etc\...` file to modify any configuration option that is used by the 7-Mode Transition Tool. This file contains information about all of the configurable options that are necessary for the tool to operate.

About this task

The file contains various options; for example, you can specify the port on which the tool service starts, and the port that the tool uses to communicate with the 7-Mode system or cluster.

Steps

1. From the system in which the 7-Mode Transition Tool is installed, open the `$INSTALL_DIR\etc\conf\transition-tool.conf` file from the installation directory, and then modify it.

Port 8443 or 8088 must be available for the 7-Mode Transition Tool to communicate with the 7-Mode system and cluster. If port 8443 or 8088 is not available or if you want to use a different port, you must change the port specified by the `tool.https.port` option in the `transition-tool.conf` file. If port 8088 is not available or if you want to use a different port, you must change the port specified by the `tool.http.port` option in the `transition-tool.conf` file.

2. Restart the 7-Mode Transition Tool service for the new values to take effect:

If your system type is...	Do the following..
Windows	<ol style="list-style-type: none"> a. Click Start > Control Panel > System and Security > Administrative Tools > Services. b. Right-click the NetApp 7-Mode Transition Tool service, and then click Stop. c. Right-click the NetApp 7-Mode Transition Tool service again, and then click Start.
Linux	Run the following command: <pre>service transition-service restart</pre>

3. After the 7-Mode Transition Tool service is restarted, add the 7-Mode system and cluster credentials again.

Troubleshooting issues

You need to be aware of some of the common issues with the 7-Mode Transition Tool and the steps to resolve them.

Tool installation fails with an incompatible OS error

Installation of the 7-Mode Transition Tool fails with the error message `7-Mode Transition Tool is not compatible with this version of Windows.`

Workaround

1. Right-click the `NetApp_7ModeTransitionTool_Setup.exe` file, and then select **Properties**.
2. In the Compatibility tab, click **Change settings for all users**.
3. Verify that the **Run this program in compatibility mode for:** check box is not selected, and then click **Apply**.

Installation or uninstallation of the 7-Mode Transition Tool is blocked

When you use the 7-Mode Transition Tool installer or the uninstaller to perform any operation (such as install, repair, reinstall, upgrade, uninstall), the following error message is displayed: `Another instance of NetApp 7-Mode Transition Tool Setup or Uninstall is running. Only one instance can run at a time.`

Workaround

Before you begin, ensure that there are no open instances or dialog boxes of the 7-Mode Transition Tool. Otherwise, you might have to perform the steps again.

1. Open **Registry** by clicking **Start**.
2. In **Search programs and files**, enter `RegEdit`.
3. When Registry Editor is open, locate the `HKEY_LOCAL_MACHINE` registry hive.
4. Expand the `HKEY_LOCAL_MACHINE` hive by clicking the expand icon to the left of the folder icon.
5. Continue to expand the registry keys and subkeys until you locate `HKEY_LOCAL_MACHINE\SOFTWARE\NetApp\7-Mode Transition Tool`.
6. Click **7-Mode Transition Tool**.
7. Right-click `INSTALLATION_STATUS`, and select **Modify**.
8. Change the value from `INSTALLER_RUNNING` to `INSTALLED`, and click **OK**.

You should now be able to perform any operation using the 7-Mode Transition Tool installer or the uninstaller.

Reinstalling or upgrading the 7-Mode Transition Tool fails on Windows system

This section provides information about the error when you reinstall or upgrade the 7-Mode Transition Tool on Windows system. It also provides the reason for the error and the steps to resolve the error.

Message

```
Another instance of NetApp 7-Mode Transition Tool setup or  
uninstall is running. Only one instance can run at a time.
```

Cause

Some of the files in the 7-Mode Transition Tool installation folder are open.

Corrective action

1. Close all of the 7-Mode Transition Tool installation files.
2. Open the registry entry for 7-Mode Transition Tool:
 - a. Check the **INSTALLATION_STATUS** field.
 - b. If the value is `INSTALLER_IS_RUNNING`, change it to `INSTALLED`.
3. Retry reinstalling or upgrading the tool.

Windows Program Compatibility Assistant notification displayed while installing the tool

Sometimes while installing the tool, you receive the Windows Program Compatibility Assistant notification that the program might not have installed correctly. This notification does not necessarily indicate that the program did not install correctly.

You can ignore this notification by clicking **This program installed correctly**.

Copyright information

Copyright © 1994–2017 NetApp, Inc. All rights reserved. Printed in the U.S.

No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark information

Active IQ, AltaVault, Arch Design, ASUP, AutoSupport, Campaign Express, Clustered Data ONTAP, Customer Fitness, Data ONTAP, DataMotion, Fitness, Flash Accel, Flash Cache, Flash Pool, FlexArray, FlexCache, FlexClone, FlexGroup, FlexPod, FlexScale, FlexShare, FlexVol, FPolicy, Fueled by SolidFire, GetSuccessful, Helix Design, LockVault, Manage ONTAP, MetroCluster, MultiStore, NetApp, NetApp Insight, OnCommand, ONTAP, ONTAPI, RAID DP, RAID-TEC, SANSscreen, SANshare, SANtricity, SecureShare, Simplicity, Simulate ONTAP, Snap Creator, SnapCenter, SnapCopy, SnapDrive, SnapIntegrator, SnapLock, SnapManager, SnapMirror, SnapMover, SnapProtect, SnapRestore, Snapshot, SnapValidator, SnapVault, SolidFire, SolidFire Helix, StorageGRID, SyncMirror, Tech OnTap, Unbound Cloud, and WAFL and other names are trademarks or registered trademarks of NetApp, Inc., in the United States, and/or other countries. All other brands or products are trademarks or registered trademarks of their respective holders and should be treated as such. A current list of NetApp trademarks is available on the web.

<http://www.netapp.com/us/legal/netapptmlist.aspx>

How to send comments about documentation and receive update notifications

You can help us to improve the quality of our documentation by sending us your feedback. You can receive automatic notification when production-level (GA/FCS) documentation is initially released or important changes are made to existing production-level documents.

If you have suggestions for improving this document, send us your comments by email.

[*doccomments@netapp.com*](mailto:doccomments@netapp.com)

To help us direct your comments to the correct division, include in the subject line the product name, version, and operating system.

If you want to be notified automatically when production-level documentation is released or important changes are made to existing production-level documents, follow Twitter account @NetAppDoc.

You can also contact us in the following ways:

- NetApp, Inc., 495 East Java Drive, Sunnyvale, CA 94089 U.S.
- Telephone: +1 (408) 822-6000
- Fax: +1 (408) 822-4501
- Support telephone: +1 (888) 463-8277

Index

7-Mode Transition Tool

- installing and uninstalling on Linux [12](#)
- installing on Linux [12](#)
- installing on Windows systems [9](#)
- logging in to web interface [10](#)
- logging in using the web interface [10](#)
- modifying the configuration file [15](#)
- prerequisites for installing or uninstalling on Windows systems [7](#)
- supported on Linux [5](#)
- supported on Windows [5](#)
- system requirements for Linux [12](#)
- system requirements for Windows [7](#)
- uninstalling on Linux [13](#)
- uninstalling on Windows systems [11](#)
- unsupported on Linux [5](#)
- unsupported on Windows [5](#)

- 7-Mode Transition Tool is not compatible with this version of Windows
workaround [16](#)

A

- access
 - enabling login for users not in Administrator group [9](#)

B

- browsers
 - supported versions for the 7-Mode Transition Tool web interface [7](#)

C

- client requirements
 - for the 7-Mode Transition Tool, Windows [7](#)
- comments
 - how to send feedback about documentation [20](#)
- configuration file
 - modifying [15](#)
- copy-based transition
 - comparison with copy-free transition [4](#)
 - data migration that you can perform [4](#)
- copy-free transition
 - comparison with copy-based transition [4](#)
 - data migration that you can perform [4](#)

D

- deciding the transition method
 - copy-free transition vs. copy-based transition [4](#)
- documentation
 - how to receive automatic notification of changes to [20](#)
 - how to send feedback about [20](#)

E

- error messages
 - 7-Mode Transition Tool installer is blocked [16](#)

F

- feedback
 - how to send comments about documentation [20](#)

H

- hardware requirements
 - for the 7-Mode Transition Tool, Windows [7](#)

I

- incompatible OS error
 - tool installation fails [16](#)
- information
 - how to send feedback about improving documentation [20](#)
- installation
 - workaround for blocked installation or uninstallation [16](#)
- installation fails
 - incompatible OS error [16](#)
- installing
 - 7-Mode Transition Tool on Windows systems [9](#)
 - 7-Mode Transition Tool on Windows systems, prerequisites for [7](#)
 - 7-Mode Transition Tool, Linux [12](#)

L

- Linux
 - installing 7-Mode Transition Tool [12](#)
 - supported features, 7-Mode Transition Tool [5](#)
 - system requirements for the 7-Mode Transition Tool [12](#)
 - uninstalling 7-Mode Transition Tool [13](#)
 - unsupported features, 7-Mode Transition Tool [5](#)
- logging in
 - to the 7-Mode Transition Tool [10](#)
- login access
 - for users not in Administrator group [9](#)

R

- reinstallation fails
 - on Windows, corrective action [17](#)

S

- server configuration requirements
 - for the 7-Mode Transition Tool, Windows [7](#)
- software requirements

- for the 7-Mode Transition Tool, Windows [7](#)
- suggestions
 - how to send feedback about documentation [20](#)
- system requirements
 - for the 7-Mode Transition Tool on Linux [12](#)
 - for the 7-Mode Transition Tool, Windows [7](#)

T

- transition
 - installing 7-Mode Transition Tool on Windows systems [9](#)
 - modifying the configuration file for [15](#)
 - using the 7-Mode Transition Tool [4](#)
- transition methods
 - copy-based transition compared with copy-free transition [4](#)
- Transition to ONTAP
 - using the 7-Mode Transition tool [4](#)
- transition-tool.conf file
 - modifying [15](#)
- troubleshooting
 - installation or uninstallation is blocked [16](#)
 - reinstallation or upgrade fails [17](#)
- Twitter
 - how to receive automatic notification of documentation changes [20](#)

U

- uninstalling
 - 7-Mode Transition Tool on Windows systems [11](#)
 - 7-Mode Transition Tool on Windows systems, prerequisites for [7](#)
 - 7-Mode Transition Tool, Linux [13](#)
- upgrade fails
 - on Windows, corrective action [17](#)
- users
 - enabling login for users not in Administrator group [9](#)

W

- web interface
 - troubleshooting [16](#)
- web interface requirements
 - for the 7-Mode Transition Tool, Windows [7](#)
- Windows
 - supported features, 7-Mode Transition Tool [5](#)
 - system requirements for the 7-Mode Transition Tool [7](#)
 - unsupported features, 7-Mode Transition Tool [5](#)
- Windows systems
 - installing 7-Mode Transition Tool [9](#)
 - prerequisites for installing or uninstalling the 7-Mode Transition Tool [7](#)
 - uninstalling the 7-Mode Transition Tool [11](#)